

How to install Wine

To install WINE, type the following command on the terminal console-

```
sudo apt-get install wine
```



Check Wine installation on the Desktop

Alternately, Wine version for Ubuntu can be downloaded from www.winehq.org using any browser. It also helps to install Wine directly from that site. In this case, Ubuntu Desktop should have direct internet connectivity.

How to run an application

Once Wine installation is completed, download Windows executable (.exe) file and later right click on the file icon to Open it with Wine Program Loader.

Setting up SMB Share

Samba is a tool that makes sharing of files and devices across computers over a network in a more secure way, irrespective of the operating systems involved.

To enable you to mount and access the shared Windows filesystem/directory, Samba is configured as per the steps mentioned below:

Step 1 - Install cifs-utils package on the desktop. For installation type the following command -

```
sudo apt-get install cifs-utils
```

Step 2 - Create a directory where the shared drive can be mounted.

```
sudo mkdir /media/Share
```



Setting SMB Share using Samba