

Recommended Resolution: Verify that the drivers for all the display adaptors on the computer are correct and updated. Remove the display adaptors and reboot. Windows will automatically detect the adaptors and configure them.

If the device is not a display adaptor, then remove the device and reinstall it using the Add Hardware Wizard.

Code 24

Code Meaning: Windows couldn't detect the device. This error may happen if the device has been set for removal.

Recommended Resolution: Verify that the hardware is working and that the physical installation is correct. Remove the device from Device Manager. Reinstall it using the Add Hardware Wizard. Update the device driver to the latest.

Code 25

Code Meaning: (Not applicable to Windows XP) The device installation has not yet been completed.

Recommended Resolution: Restart the computer. Windows may require to be reinstalled depending on whether the reboot solves the problem or not.

Code 26

Code Meaning: (Not applicable to Windows XP)

The device did not load or not all the drivers were installed.

Recommended Resolution: Remove the device from Device Manager. Reinstall using the Add Hardware Wizard.

Code 27:

Code Meaning: (Not applicable to Windows XP)

The Windows Registry entry describing the resources for this device is not valid.

Recommended Resolution: Remove the device from Device Manager. Reinstall it using the Add Hardware Wizard.