

Cause 2: The BIOS settings are incorrect.

Solution 2: Restart the computer and enter the BIOS setup screen. If you have changed any settings, restore them to the previous values. If you are not sure about the previous values or haven't changed the settings, select the Load Fail-safe Defaults (this could also be "Factory Defaults", "BIOS Setup Defaults", etc.) option and reboot.

Cause 3: There might be a hard disk failure or data corruption in the boot records

Solution 3: Insert the Windows XP installation CD and restart the computer. On the "Welcome to Setup" screen, press [R] to start the Recovery Console. You will be prompted for the administrator password. Type in the password, or if the password is blank, hit [Enter]. At the command prompt, type in "chkdsk". This will run the Checkdisk utility that will scan the hard disk for any faults. Checkdisk may report a hardware failure or errors on your disk. If it does, it is best to take your PC to a repair professional.

► **Problem:** You receive an error message when Windows XP starts.

Cause: A recently installed file or service or software program is incompatible with Windows XP and is preventing it from starting. Look carefully at the error message. If a file or service name is referred to in the error message, then you can troubleshoot by either clean booting or by stopping the service.

Solution 1a: To perform a clean boot in Windows XP, use the following steps:

1. Start the system configuration tool by going to Start > Run, typing in "msconfig", and pressing [Enter]
2. Click Selective Startup and clear the following checkboxes: "Process System.ini File", "Process Win.ini File", and "Load Startup Items".
3. Select the Services tab and click the "Hide All Microsoft Services" checkbox, and then select "Disable All".
4. Click OK and then "Restart" to restart your system.
5. When Windows restarts, if the error doesn't occur, re-open "msconfig" and check the "Process System.ini File" checkbox,