

2.4.2 PCI and AGP Options

8-bit I/O Recovery Time

Options: N/A, 1, 2, 3, 4, 5, 6, 7, 8

Recommended Setting: N/A

Explanation: Synchronises the PCI-ISA bus. If don't have an ISA card it does nothing.

16-bit I/O Recovery Time

Options: N/A, 1, 2, 3, 4

Recommended Setting: N/A

Explanation: Same as 8-bit, but for 16-bit transactions. Does nothing without an ISA card.

AGP 2x Mode and AGP 4x Mode

Options: Enabled, Disabled

Recommended Setting: Enabled

Explanation: This enables or disables AGP 2x or 4x depending on what your BIOS shows. Even if your card is AGP 2x and you set it to 4x, the chipset will fall back to 2x, so there is no harm in enabling this setting.

AGP Aperture

Options: Disabled, 8MB, 16MB, 32MB, 64MB, 128MB, 256MB

Recommended Setting: Disabled

Explanation: Controls how much system RAM the AGP card is allowed to use for AGP texturing. If you're not a heavy gamer, and if you don't work too much with 3D applications, there's no point assigning an AGP aperture. Also, if you've got, say, only 256 MB of RAM, you don't have RAM to spare—hence the AGP Aperture should be disabled.

Assign IRQ to PCI/AGP VGA

Options: Enabled, Disabled

Recommended Setting: Enabled

Explanation: Tells the BIOS to assign an IRQ to the display. Useful for Windows 95/98/ME. Makes no difference to Windows 2000/XP if enabled.