

CPU to PCI Write Buffer

Options: Enabled, Disabled

Recommended Setting: Enabled

Explanation: Sets the priority to the CPU when writing to the PCI bus. Better performance if enabled. May cause instability with some sound cards.

Fast Writes

Options: Enabled, Disabled

Recommended Setting: Disabled

Explanation: There's a very slight performance increase if enabled. But it causes instability with video cards that doesn't support Fast Writes.

I/O Recovery Time

Options: Enabled, Disabled

Recommended Setting: Disabled

Explanation: Enable this if you are facing problems with any ISA cards you may have.

Master Priority Rotation

Options: 1 PCI, 2 PCI, 3 PCI

Recommended Setting: Depends on your configuration.

Explanation: Controls CPU access to the PCI bus. If you have RAID and SCSI, 3 PCI is better. With NICs and TV-Tuners, 1 PCI is better. You will have to experiment for your configuration.

Passive Release

Options: Enabled, Disabled

Recommended Setting: Depends on how your system responds.

Explanation: Allows ISA devices to write to the Passive Release Buffer without waiting for the PCI bus. Enable for better performance; disable if your ISA cards or NICs have problems.

PCI #2 Access #1 Retry

Options: Enabled, Disabled

Recommended Setting: Enabled

Explanation: Works with the CPU to PCI Write Buffer. Enabling