

5.3. Sandbox From Contours

The Sandbox From Contours tool does just exactly what it says, that is, helps you to create a sandbox (a TIN) from contours. So how exactly would you manage to make contours? You could do any one of the following:

- a) Create contour lines by using the Freehand Tool. You can activate the Freehand tool either by clicking Draw > Freehand in the drop down menu above, or clicking on the Freehand button (which looks like a shapeless squiggle) in the Drawing toolbar.
- b) Import contour lines from another file.

Whatever you choose to do, there's one thing you have no choice about—the lines must be offset in height (vertically displaced) from the ground plane.


5.3.1 Creating Contoured Boxes

It's a piece of cake to use contour lines to create a sandbox.


Draw contour lines (as many as you like)—lines which are irregular and randomly scribbled would do for the present. Just make sure that the lines are offset from the ground plane.

Use the select tool and select all the lines you've drawn (the line's will turn blue once selected).

Click Draw > Sandbox > From



Squiggly scribbles



Terra not so firma