

5.8. The Add Detail and Flip Edge Tools


As you gravitate towards more complex models, you'll find the need to work on a really minute scale on the terrain you're creating. To facilitate control over your TIN at such a micro level, SketchUp provides two tools: The Add Detail Tool and the Flip Edge Tool.

Although this results in better terrains and smoother surfaces, this could seriously slow down performance because the number of calculations increases drastically, so must be used with prudence.

5.8.1. Details about Adding Details

To make a terrain more detailed, do the following:

- Make a TIN.



Here's a Sandbox from Scratch to begin with

- Activate the Add Detail Tool as specified above. The cursor now becomes an arrow.

Make sure that the TIN is ungrouped (if it isn't, right click and click on the Explode option in the menu context menu that appears).

- Click somewhere on or in the TIN. The point at which you click will set the new vertex for triangulation.

You can select different objects, using [Shift] to extend your selection and dragging the mouse around to select multiple items.

- If you drag the mouse up and down after choosing a vertex, you'll see the point (and the other neighbourhood points) of the TIN being offset from the ground plane. If you want to ensure that the offset is perpendicular to the TIN, simply hold down the