

Select from the cursor to the next sample. . .	[Shift] + [+] (keypad)
Select from cursor to the previous sample. . .	[Shift] + [-] (keypad)
Select 10 samples past the current cursor. . .	[Ctrl] + [Shift] + [+] (keypad)
Select 10 samples prior to the current cursor.	[Ctrl] + [Shift] + [-] (keypad)
Snap to time.	[T]
Snap edge to time.	[Shift] + [T]
Snap to next zero crossing.	[Z]
Snap edge to next zero crossing.	[Shift] + [Z]
Switch the selection through the channels in a multichannel file.	[Tab]/[Shift] + [Tab]
[Shift] current selection to the left by the length of the selection.	[<]
[Shift] current selection to the right by the length of the selection.	[>]
Cut the current selection length in half.	[:]
Double the current selection length.	[']
Rotate audio.	[:]
Restore previous five time selections.	[Backspace]
Toggle last selection/cursor position.	[S] or [/]
Create a loop from the current selection. . . .	[Alt] + [Shift] + [L]
Create a loop from the current selection without displaying the Edit Sample dialog. . .	[Alt] + [L]

5.2.5. Navigation

Function	Shortcut
Save a view in cell <Number> where <Number> ranges from 1 to 8.	[Ctrl] + [Shift] + <Number>
Restore a view using cell <Number> where <Number> ranges from 1 to 8.	[Ctrl] + <Number>
Move cursor to corresponding marker or select corresponding region	0-9 keys (not keypad)
Increase time magnification (zoom in).	[Up Arrow] or Mouse Wheel Up