

Decrease time magnification (zoom out). . . .	[Down Arrow] or Mouse Wheel Down
Increase level magnification.	[Shift] + [Up Arrow]
Decrease level magnification.	[Shift] + [Down Arrow]
Zoom to selection if a selection exists; otherwise Zoom In Full.	[Ctrl] + [Up Arrow]
Zoom normal (zooms to default zoom ratio set in Preferences).	[Ctrl] + [Down Arrow]
Display custom zoom ratio 1.	[1] (keypad)
Display custom zoom ratio 2.	[2] (keypad)
Pan data window up if zoomed in vertically. Pan data window down if zoomed in vertically.	[Ctrl] + [Shift] + [Up Arrow] [Ctrl] + [Shift] + [Down Arrow]
Switch cursor to opposite end of selection. . .	[5] (keypad)
Set Mark In at the current cursor position. .	[I]
Set Mark Out at the current cursor position. .	[O]
Play or stop the contents of the data window in default mode.	[Space] or [F12]
Play all.	[Shift] + [Space] or [Shift] + [F12]
Play/Pause.	[Enter] or [Ctrl] + [F12]
Switch play mode between Normal, Plug-In Chainer, Play as Sample, and Play as Cutlist playback modes.	[X]
Pause playback and leave the cursor at the current position.	[Enter]
Stop or cancel the current action (including playback).	[Esc]
Toggle looped playback.	[Q]
Seek cursor on playback	[F]
Preview cut (skip selection on playback with pre-roll).	[Ctrl] + [K]
Play to cursor with pre-roll.	[Ctrl] + [Shift] + [K]
Scrub playback	[J], [K], or [L]