

-s: Clears the system file attribute.

+h: Sets the hidden file attribute.

-h: Clears the hidden file attribute.

[Drive :][Path] FileName: Specifies the location and name of the directory, file, or set of files for which you want to display or change attributes. You can use wildcard characters (that is, ? and *) in the FileName parameter to display or change the attributes for a group of files.

/s: Applies attrib and any command-line options to matching files in the current directory and all of its subdirectories.

/d: Applies attrib and any command-line options to directories.

Bootcfg

Configures, queries, or changes Boot.ini file settings.

Syntax:

```
bootcfg [/[ sub-utility]
```

Sub-utilities:

/Copy

Makes a copy of an existing boot entry [operating systems] section for which you can add OS options to.

/Delete

Deletes an existing boot entry in the [operating systems] section of the BOOT.INI file. You must specify the entry# to delete.

/Query

Displays the current boot entries and their settings.

/Raw

Allows you to specify any switch options to be added for a specified boot entry.

/Timeout

Allows you to change the Timeout value.