

notification is given.

Of course, the entire case is academic in case the first “Allow Devices to connect” is unchecked.

Other options on the Options tab let you turn on or turn off the Bluetooth icon in the notification area and restore default settings.

Typically, your Bluetooth enabled computer will discover other devices. Therefore, you only have to turn on the Turn Discovery On option when your computer acts as a device. For example, you might want to turn on this option when your computer is connected to another computer by a Personal Area Network (PAN). When computers are connected by a PAN, one of the computers must have discovery turned on.

By default, discovery is not turned on in Windows XP SP2, because a discoverable Bluetooth device may be less secure than a device that is not discoverable. We recommend that you keep the Turn Discovery On check box cleared unless you want another Bluetooth device to discover the computer. When the connection is complete, the Add Device Wizard turns off discovery automatically.

Joining a personal area network

Personal Area Networking (PAN) provides ad hoc networking between Bluetooth devices. All devices that you want to network must support PAN in order to create a PAN network. To join a PAN network, you can use any one of the following methods:

- Click the Join a Personal Area Network option in the Bluetooth taskbar icon menu.
- Double-click the Bluetooth Network Connection icon in the Network Connections item in Control Panel.
- Click View Bluetooth network devices in the Network Tasks pane in Network Connections.

Each of these methods opens the Bluetooth Personal Area Network Devices dialogue box. This box displays a list of devices to which you can connect. You can also add or remove devices from this list by using the options at the bottom of the dialogue box.

To make a connection, select the device that you want to connect to, and then click Connect. When the connection is complete, TCP/IP networking is available between your