

Adding linked libraries

To add linked libraries and their search paths:

Select **C/C++ Build > Settings** in the Properties Window. From the Configuration drop-down list, select the Target-Debug or Target-Release configuration. In the Tool Settings tab, select **bada C++ Linker > Miscellaneous**. Define the libraries to be used under Other objects. To save the settings, click Apply.

Adding shared libraries

To add shared libraries and their search paths:

1. In the bada IDE Project Explorer, add a lib folder in your application project.
2. Copy the shared libraries to the newly created lib folder.

When you add the shared libraries to the target device, the file name of the libraries must start with lib, for example, libLIBRARY.so.

To use the shared libraries in the Emulator, also copy them to the `\<BADA_SDK_HOME>\Model\<Device_model>\Emulator` folder.

3. In the Properties window, select **C/C++ Build > Settings**.
4. From the Configuration drop-down list, select the appropriate build configuration.
5. In the Tool Settings tab, select **bada C++ Linker > Libraries**.
6. Add the shared libraries to be used under Libraries (-l).
7. Add the library names without prefix and file extensions, for example, LIBRARY.

Check whether the default library path `${PROJECT_ROOT}/lib` exists under Library search path (-L). If not, set the newly created lib folder as the search path.

8. To save the settings, click Apply. 

For detailed
technical
information, visit
developer.bada.com