

```

• Button *pButton;
• pButton = static_cast<Button*>(GetControl(L"IDC_
BUTTON1", false));
• }

```

Managing Language Resources

You can manage the language resources used in localising your application in UI Builder. Localised string resources are useful for resource management and localisation, because you can create your application in one language and then add the corresponding strings in the other languages that you want to support.

To create string resources:

1. In the Resource Explorer, double-click String.
2. Add new strings by right-clicking the work area and selecting Insert.
3. Add new languages by right-clicking the work area and selecting Language setting.

For detailed
technical
information, visit
developer.bada.com

The following source code snippet demonstrates

the use of strings from the string resources:

```

• Application* pApp = Application::GetInstance();
• String str1;
• r = pApp->GetAppResource()->GetString("IDS_ STRING1",
str1);

```

English is used if a string resource does not exist for a particular language. However, if a string resource does not exist even for English, the `GetString()` method fails.

To use the different languages defined in the string resources on the device, go to **Settings > General > Language > Display** in the device menu, and select the corresponding language. 